

Inexpensive Water Motion Measurement Devices and Techniques and Their Utility in Macroalgal Ecology: A Review

Sophie D. Boizard* and Robert E. DeWreede

Department of Botany, The University of British Columbia, Vancouver, B.C. Canada V6T 1Z4.

* Corresponding author, E-mail: boizard@interchange.ubc.ca

ABSTRACT: Water motion and wave impact are, together, major determinants of the abundance and distribution of benthic intertidal marine organisms. Relatively simple techniques and devices that measure water motion and wave impact exist, and range from qualitative approaches (e.g. measurements of fetch), to integrative measures (dissimilar metals), to one-time maximum wave impact devices (drogues). We discuss the advantages and disadvantages of these devices and techniques, and provide examples of their use in marine benthic ecology. More complex devices such as arrays of electronic sensors that measure wave height and water motion continuously over very short time intervals are more expensive and are not discussed in detail.

KEYWORDS: water motion, drogues, waves, gypsum blocks, dissimilar metals, macroalgal ecology.

INTRODUCTION

Water motion is a major force driving the ecology and evolution of macroalgae. Water motion can affect macroalgae directly through physical disturbances causing tissue breakage or dislodgement of the holdfast¹⁻⁶, or by increasing the flow at the surface of the thallus, favouring nutrient and gas exchange and thus algal productivity and growth⁷⁻⁹. Water motion can also directly affect gamete transport, spore dispersal and settlement success¹⁰⁻¹². Indirectly, water motion can affect survival of macroalgae and community composition by modifying the behaviour of herbivores, the importance of biotic interactions, and the magnitude of thermal and desiccation stress¹³⁻²⁰. For example, Wing et al.¹⁶ showed that water motion has a strong effect on light in multilayered macroalgal stands; mechanical disruption of the canopy cover by waves travelling through it increases light penetration to the understory and decreases self-shading within the canopy itself. Despite its importance, precise measurement of water motion *in situ* remains a challenge.

The goal of this paper is to review water motion measurement techniques and their utility in macroalgal ecology. As such, this is not an exhaustive review as we emphasize techniques that are appropriate for measurement of flow on wave-swept shores and subtidal environments. We focus on devices that can be readily constructed, are relatively inexpensive to build, and are simple to maintain and read in the field; such instruments facilitate placement of multiple devices at different locations, enabling the investigator to

compare water motion at different locations simultaneously. We refer the reader to the literature for a description and discussion of the use of electronic devices to measure water motion.

The methodology for measuring water motion varies from cartographic approaches to the construction and placement of physical devices at the appropriate study sites. Cartographic methods may incorporate measurements of open-water (fetch) bordering a study site, frequency of winds blowing from specific directions, and sometimes, local bottom topography, to obtain an Exposure Index. Physical devices include those in which weight lost to dissolution is used to estimate water movement, and others that measure the actual force of wave impact on a shore. Some devices measure water flow, others measure the force generated by water flow and wave impact; which technique or device is used depends on the requirements of the investigator. Each technique is described separately, along with suggestions for use. We also include a summary table that lists the various techniques/devices discussed, their approximate cost, and advantages and disadvantages.

FETCH BASED INDICES

Fetch-related exposure indices are based on wind speed and fetch (the maximum distance wind can blow unimpeded across a stretch of water) to predict the size (height) of wind-generated waves.

The index described here has been developed by the Physical Shore-Zone Mapping Task Force of British

Columbia, Canada²¹, and is based on standard engineering practices for estimating wave heights for a particular shore unit or site²². Engineering practices involve the use of complex wave climate models that combine fetch characteristics with historical wind-climate measurements and wind-wave generation, wave refraction and shoaling information. The goal of the Mapping Task Force was to develop a method for estimating wave exposure that could be easily calculated, making it accessible to non-engineers, and still retaining reasonable accuracy. The technique is intended to be part of a common set of inventory mapping standards for the coast of British Columbia. Since this particular method ignores local wind climate and wave refraction, it should be considered as a first approximation of wave exposure.

The method takes into account two indices of fetch: modified effective fetch and maximum fetch. Modified effective fetch involves the measurement for a particular site of fetch distances along three vectors, the shore-normal (perpendicular to the general trend of shore line) and 45° to left and right of the shore-normal. Modified effective fetch is calculated using the following equation:

$$F_e = \frac{-\sum \cos \chi_i \Delta F_i}{-\cos \chi_i}$$

where F_e is the effective fetch in km, θ_i is the angle between the shore normal and the direction (0°, 45° to the left and 45° to the right), and F_i is the fetch distance in km along the relevant vector²². Modified effective fetch estimates the contribution of locally wind-generated waves while maximum fetch accounts for the contribution of waves generated in areas remote from the site such as the open ocean, but which can propagate onto the shore. Maximum fetch provides an index of swell waves and is defined as the maximum fetch distance in km measured from the site. By convention, a value of 1000 km is used when open-ocean fetches occur, that is fetch lines directed into the open-ocean²¹.

Measurements of modified effective fetch and maximum fetch are then used to determine the wave exposure class of a particular site (Table 1). Exposure classes are derived from prior knowledge and cross-tabulation of maximum fetch and modified fetch measurements (Table 1). This method has been compared to an intertidal biotic assemblage-based index of wave exposure and is reported to agree reasonably well, showing 75% agreement between the two methods²¹.

A fetch-based index offers at most a rough measure of wave exposure, it has the advantage of being objective and repeatable, i.e. different workers will obtain the same index. It is a rough measure because it averages wave exposure over distance and time, and thus has

limited spatial and temporal resolution. As well, this procedure as described here does not factor in nearshore topography, an important factor in how waves build onto the shore (however see²²⁻²⁴). This metric is simple to compute, though potentially time-consuming, and requires no presence on the shore.

BIOLOGICALLY DEFINED EXPOSURE INDICES

Ballantine²⁵ and Lewis²⁶ were among the first to propose a biologically defined exposure index (= BDEI) based on the abundance of marine organisms and their observed distribution in response to wave impact. This approach is not universally applicable as the composition and sensitivity of communities differs from one site to another, precluding direct comparisons over larger spatial scales²⁵⁻²⁶. BDEI also assumes that no factors other than wave action influence the biological communities examined²⁵⁻²⁷. Bell and Denny²⁷ showed that a site classified, *a priori*, as moderately exposed using qualitative observations of water motion and community assemblages, experienced much greater hydrodynamic disturbance (as measured with drogues) than was first assumed, suggesting caution in the use of qualitative descriptions and biological indices to explain and predict specific ecological patterns and processes.

Once a BDEI is constructed, it does have the benefit of integrating the organisms of interest (to the ecologist) into the index, even if these organisms have a limited range. A disadvantage of the BDEI is that it incorporates no direct measure of wave exposure; hence it cannot be directly compared to any of the other measures discussed here.

Others have used morphological measurements of macroalgae as an indicator of water motion. But using morphological patterns to determine exposure to water motion is a circular argument, as are indices based on

Table 1. Wave exposure classes based on modified-effective fetch and maximum fetch (after²¹).

Modified-effective fetch (km)					
Max fetch (km)	<1	1-10	10-50	50-500	>500
<10	VP	P	n/a	n/a	n/a
10-50	n/a	SP	SP	n/a	n/a
50-500	n/a	SE	SE	SE	n/a
>500	n/a	n/a	SE	E	E

VP: Very protected, usually the location of all weather anchorages, marinas and harbours.
P: protected, usually areas of provisional anchorages and low wave exposure except in extreme winds.
SP: semi-protected, waves are low most of the time except during high winds.
SE: semi-exposed, swells generated in areas distant from the shore unit create relatively high wave conditions; during storms, extremely large waves create high-wave exposures.
E: exposed, high wave conditions usually prevail within this exposure category, which is typical of open-ocean conditions.




Fig 1. a) Picture of a candy 'rake' used to measure the rate of dissolution of sucrose candy (Lifesavers™) as an estimate of relative water motion. b) Picture of gypsum blocks used to measure the rate of dissolution of gypsum as an estimate of relative water motion; i) before and ii) after immersion (note: lower block in ii) was lost). c) Picture of a dissimilar metal unit used to measure the rate of dissolution of zinc as an estimate of relative water motion (picture courtesy of S. Sandwith). The sampling unit consists of a PVC pipe with three pairs of a zinc rod and a copper pipe held together with rubber bands; ii) Picture of unit in situ, (picture courtesy of A. Griffiths). d) Picture of a dynamometer used to measure maximum wave velocities on wave-swept shores. i) Sampling unit out of the water showing swivel at top end attached by cable-ties to an eyebolt; ii) Picture of a dynamometer inserted into a hole drilled into the rock exposing only the drag element.

biological assemblages: a shore is considered wave-exposed because kelps, for example, *Nereocystis luetkeana*, have smooth, strap-like (narrow but thick) blades, and *Nereocystis*' blades are smooth and strap-like because they are subjected to high wave exposure.

METHODS BASED ON DISSOLUTION

Another approach to measuring water movement is to measure weight loss of a given material, such as sucrose candies (Lifesavers™, gypsum, or zinc, as a function of water movement. These methods have been widely used as a measure of 'water motion' and have proven useful for studies involving question of mass/heat transfer or nutrient/particle delivery to and from organisms²⁸⁻³⁰, but provide little information regarding instantaneous flow magnitudes or imposed hydrodynamic forces.

SUCROSE CANDIES

Shaughnessy³¹ and Martel³² measured weight loss of sucrose candies (Lifesavers™ that were submerged at each site for a period of 2 min. to assess differences in wave exposure among sites. Koehl and Alberte²⁹ used sucrose candies attached directly to the blade of the kelp *Nereocystis luetkeana* to compare water velocities along blades of different morphologies. In each case, weights of the candies are determined prior to immersion, and once again after immersion and drying. One technique for immersion is to attach pre-weighed candies to the prongs of a rake-like device, with the candies held in place by rubber stoppers (Fig. 1a). The rake is immersed for a short, measured time period (approx. 2 min.), and the candies serve as replicate measures of water motion at the site.

This method is rapid, cheap, and repeatable over a short time frame. If different sites are to be compared, it is useful to make the measurements simultaneously at each site, to minimize differences due to tidal elevations and weather.

GYP SUM BLOCKS

This technique is similar in logic and approach to the sucrose candies technique but utilizes ice-cube sized gypsum (CaSO_4 , plaster of Paris) casts glued, for example, to Plexiglas cards that can be variously attached to rocks in the intertidal or subtidal (Fig. 1b), or to poles anchored in the subtidal. Some authors have also successfully used gypsum buttons or nodules glued or directly moulded to a paper clip that can be clamped directly to the thallus of a kelp⁷. As with the sucrose candies, clod-cards are pre-weighed, immersed in water for 24 - 72 hrs, dried, and reweighed. The loss in weight provides a relative measure of water motion at a site, and multiple measurements can be compared

among sites.

Measurements of weight loss can be converted to water velocities by using a standardized calibration curve. Such a curve can be obtained by immersing some blocks in standing water and others in waters of known velocities, all for a known length of time. However, at best, such calibration curves offer an approximation, as rates of gypsum dissolution have been found to vary with the shape of the cast, the temperature and salinity of the surrounding seawater, the abrasive action of sediment or adjacent macroalgae, and erosion due to grazers³³⁻³⁵. Furthermore, Porter *et al.*³⁶ suggest that gypsum dissolution rates are greatly influenced by changes in the flow environments from steady to fluctuating flow speeds and argue that the gypsum dissolution technique should not be used as an "universal integrator of 'water motion'". If these limitations are considered, however, this technique can be used and has been used extensively as a index of relative water exposure (see³⁶ and references therein).

CORROSION RATES OF DISSIMILAR METALS

This technique is based on the fact that two metals from the opposite ends of the Noble scale when put into contact in seawater will corrode through electrolysis and galvanic corrosion³⁷. Copper and zinc are most commonly combined due to their inexpensiveness and wide availability. A measure of absolute water velocity can be estimated by converting measurements of weight loss of the zinc (the copper remaining relatively unaffected) to standard curves derived in controlled laboratory settings, e.g. immersed in water of known velocities. Each sampling unit consist of three to six pairs of copper piping and zinc rod held together by a rubber band (usually a piece of a bicycle inner tube) and attached (also by a rubber band) to a piece of PVC pipe (Fig. 1c). The PVC pipe in turn is attached to a cement block that serves as an anchor to hold the array in place (Fig. 1c). Clearly in more wave impacted sites a more solid means of anchoring, such as bolts and cement anchors, is required.

DROGUES

Disturbance and mortality due to the impact of hydrodynamic forces associated with moving water are inadequately measured by dissolution-based methods. The probability of an organism being dislodged or damaged due to the impact of a passing wave can be best estimated by determining the maximum water velocity and thus the force to which it is exposed. Drogues are instruments that measure water motion, *in situ*, by recording the maximum drag force imposed on a plate or spherical device attached to a spring. The hydrodynamic drag on the plate or sphere can be

Table 2. Summary table comparing some of the advantages and disadvantages of the various methods and instruments used for measuring flow. Refer to text for details

Method	Principle of method	Variable measured	Intertidal vs subtidal	Estimate obtained	Spatial & temporal scale	Equipment needed	Set up time	Approximate cost (CND \$)	Period of deployment	Repeated use	Limitations
Qualitative	Qualitative categorization based on personal observation and knowledge	None	Applied to both	Exposed to sheltered subjective categorization	Crude; local to regional scale	None	None	None	One time categorization	n/a	Subjective
Biological	Categorization based on knowledge of marine organisms' ecology with regards to wave exposure	Presence/absence of species	Usually intertidal	Exposed to sheltered categorization based on species assemblages present	Crude; local scale	Paper and pencil	None	Minimal	One time categorization	n/a	Based on knowledge of local marine communities' composition and their sensitivity to exposure; not applicable universally
Fetch-related cartographic method	Size of wind-generated waves depends on the fetch window (area of ocean surface over which wind can blow unimpeded)	Fetch distances, modified-fetch and maximum fetch (km)	Applied to both	Index of relative wave exposure (obtained using modified-fetch and maximum fetch matrix)	Limited: average over km and months; local to regional scale	Chart, Compass, Ruler	< 5 min per site	\$15-\$20	One time measurements	n/a	Based on cartographical data only; does not take into account effect of bottom topography on wave size or swell contribution
Sucrose Candies	Rate of dissolution (or mass loss) of an element increases with increases in water motion	Mass loss (g)	Usually intertidal, but has also been used subtidally at micro scale	Overall/cumulative or average water motion/mass flux; Index of relative wave exposure	Measurements taken over a few min; micro scale (flow around a 'broom', scale kept blade) to local scale	Candies	1.5-30 min.	\$5-\$15/unit	2 min.	No (requires new candies)	Measurements affected by flow velocities but also flow turbulences
Gypsum blocks (CaSO ₄)	As with sucrose candies	As with sucrose candies	Both intertidally and subtidally	As with sucrose candies	Average taken over 24-72 hrs; micro scale (plaster buttons) to local scale	Plaster of Paris, ice cube trays, 5 min marine epoxy, Plexiglass cards (10cmx10 cm) bolts & nuts, scale	24-72 hrs	\$20-\$50 for 24-48 blocks	24-72 hrs	No (requires new CaSO ₄ blocks)	Measurements affected by flow velocities but also flow turbulences, water temperature, salinity and abrasion by neighbouring organisms or herbivores
Dissimilar metals	Rate of electrolysis (mass loss) of zinc increases with increases in water motion	Mass loss of zinc (g)	Both intertidally and subtidally	Overall/cumulative or average water motion/mass flux; Index of relative wave exposure or absolute wave exposure if calibrated against known water flow	Average taken over 7d; local to regional scale	Zinc and copper rods, PVC piping, rubber bands, scale	1-48 hrs	\$5-\$10 /3 pairs	5-21d	Yes, but limited by rate of electrolysis	Zinc rods made from different batches of alloys will produce variable reactions and thus unreliable results; more durable than plaster, can be let in the field for longer; thus give a better average speed of variable flow; but provides no information of instantaneous flow
Drogues	An object exposed to a passing wave will experience drag force proportional to wave velocity	Spring extension (cm)	Intertidally	Maximum wave force; maximum wave velocities; Index of absolute wave exposure	Maximum over period of deployment, local to regional	Spring, CPVC piping, practice golf ball, fishing line, various fittings	24-72 hrs	\$15-\$25/unit	Minimum of one tidal cycle (12-24 hrs)	Yes	Provides a good approximation of the effective maximum velocities flexible macroalgae experience, however may underestimate water velocities experienced by organisms that are stiffer than the drogue because of time lag due to realignment of instrument

estimated directly by measuring the extension of the spring as the object is exposed to drag. The dynamometer (= drogue; Fig. 1d), now in common use, was designed by Bell and Denny²⁷, and is a modification of one developed by Jones & Demetropoulos³⁸.

Bell and Denny's²⁷ dynamometer consists of a practice golf ball (a perforated hollow plastic sphere) attached by a piece of monofilament line to a stainless steel spring housed in a Chlorinated Poly-Vinyl Chloride (CPVC) cylindrical case. As drag is exerted on the sphere, the maximum spring extension is recorded by a rubber indicator fitted snugly onto the monofilament line. The dynamometer can be either anchored to the rock by means of a stainless steel swivel in turn attached with cable ties to an eyebolt drilled into the substratum, or by inserting the CPVC housing into a hole drilled into the rock (Fig. 1d). The latter requires access to a rock drill but such placement prevents the loss of instruments due to both entanglement with algae and excessive wave surge at high wave exposure sites.

Mathematical modelling and field measurements showed that drogues provide accurate estimates of maximum water velocities on wave-swept shores when peak velocities and the period of oscillations are high. Under low peak velocities (< 5 m/s) and short-period oscillations (< 4 s), however, the deceleration of the practice golf ball and the reorientation of the housing will lead to an overestimation of the hydrodynamic force (Bell and Denny²⁷).

As drogues have come into more common use, we have listed some currently useful websites about their construction and use:

1. Dr. Mark Denny's Lab web site with a detailed step-by-step description of how to built wave dynamometers: <http://www.stanford.edu/group/denny/>
2. One source of the springs is: <http://www.asraymond.com>
3. A supplier of other parts used in the drogues is: <http://www.smallparts.com>

ELECTRONIC DEVICES

A number of electronic devices capable of continuously measuring instantaneous water velocity have also been developed for use in the intertidal^{34, 39} and the subtidal⁴⁰. Such instruments provide detailed information on water velocities and accelerations in 2 or 3 dimensions at high temporal resolutions. Detailed knowledge of *in situ* flow velocities and fluctuations is essential for studies examining propagule/larval dispersal and their settlement patterns. However, these instruments can be expensive to build and/or buy (e.g. electromagnetic current meters, acoustic doppler velocimeter), usually making simultaneous

measurements at a large number of locations not feasible.

CONCLUSION

Water motion manifests itself in a multitude of ways important to marine benthic organisms. The forces generated by waves striking the shore can tear and detach organisms, and the moving water can generate drag forces, as well as influence nutrients and physical characteristics of a body of water such as temperature, salinity, and content of gasses. Marine ecologists are frequently required to measure water motion in a way that is repeatable, inexpensive, and relevant to the research questions being investigated. We have provided an overview of such devices. Table 2 summarizes the advantages and disadvantages of each technique and device discussed, what variable each measures that is relevant to marine benthic algal ecology, and a rough estimate of cost and necessary materials.

REFERENCES

1. Koehl MAR (1984) How do benthic organism withstand moving water? *Am Zool* **24**: 57-70
2. Koehl MAR (1986) Seaweeds in moving water: form and mechanical function. In: *On the Economy of Plant Form and Function*, (Edited by Givnish TJ, pp. 603-624, Cambridge University Press, Cambridge, UK.
3. Seymour RJ, Tegner MJ, Dayton PK and Parnell PE (1989) Storm wave induced mortality of giant kelp, *Macrocystis pyrifera*, in southern California. *Estuar Coast Shelf Sci* **28**: 277-92.
4. Carrington E (1990) Drag and dislodgment of an intertidal macroalga: consequences of morphological variation in *Mastocarpus papillatus* Kutzing. *J Exp Mar Biol Ecol* **139**: 185-200.
5. Vadas RL, Wright WA and Mille SL (1990) Recruitment of *Ascophyllum nodosum*: wave action as a source of mortality. *Mar Ecol Prog Ser* **61**: 263-72.
6. Blanchette CA (1997) Size and survival of intertidal plants in response to wave action: a case study with *Fucus gardneri*. *Ecology* **78**: 1563-78.
7. Gerard VA (1982) *In situ* water motion and nutrient uptake by the giant kelp *Macrocystis pyrifera*. *Mar Biol* **69**: 51-4.
8. Hurd CL (2000) Water motion, marine macroalgal physiology, and production. *J Phycol* **36**: 453-72.
9. Stevens CL, Hurd CL and Smith MJ (2001) Water motion relative to subtidal kelp fronds. *Limnol Oceanogr* **46**: 668-78.
10. Norton TA, Fetter R (1981) The Settlement of *Sargassum muticum* Propagules in Stationary and Flowing Water. *J Mar Biol Ass UK* **61**: 929-40.
11. Vadas RL (1992) Recruitment and mortality of early post-settlement stages of benthic algae. *Br Phycol J* **27**: 331-51.
12. Gaylord B, Reed DC, Washburn L and Raimondi PT (2004) Physical biological coupling in spore dispersal of kelp forest macroalgae. *J Mar Syst* **49**: 19-39.
13. Menge BA (1976) Organization of the New England rocky intertidal community: role of predation, competition, and

- environment heterogeneity. *Ecol Monogr* **46**: 355-93.
14. Santelices B, Castilla JC, Cancino J and Schmiede P (1980) Comparative ecology of *Lessonia nigrescens* and *Durvillaea antarctica* (Phaeophyta) in central Chile. *Mar Biol* **59**(2): 119-32.
 15. Chess JR (1993) Effects of the stipe-boring amphipod *Peramphithoe stypotruripes* (Corophioidea: Ampithoidea) and grazing gastropods on the kelp *Laminaria setchellii*. *J Crust Biol* **13**(4): 638-46.
 16. Wing SR, Leichter JJ and Denny MW (1993) A dynamic model for wave induced light fluctuations in a kelp forest. *Limnol Oceanogr* **38**(2): 396-407.
 17. Tegner MJ, Dayton PK, Edwards PB and Riser KL (1995) Sea urchin cavitation of the giant kelp (*Macrocystis pyrifera* C. Agardh) holdfasts and its effects on kelp mortality across a large California forest. *J Exp Mar Biol Ecol* **191**: 83-99.
 18. Duggins DO, Eckman JE, Siddon, CE and Klinger T (2001) The interactive role of mesograzers and current flow in survival of kelps. *Mar Ecol Prog Ser* **223**: 143-55.
 19. Harley CDG and Helmuth BST (2003) Local- and regional-scale effects of wave exposure, thermal stress, and absolute versus effective shore level on pattern of intertidal. *Limnol Oceanogr* **48**(4): 1498-508.
 20. Engkvist R, Malm T and Nilsson J (2004) Interaction between isopod grazing and wave action: a structuring force in macroalgal communities in the southern Baltic Sea. *Aquat Ecol* **38**(3): 403-13.
 21. Howes D, Morris M and Zacharia M (1999) British Columbia Estuary Mapping System. Resource Inventory Committee (RIC) Report by the Coastal Task Force RIC Secretariat, Victoria BC 62pp.
 22. Coastal Engineering Research Center (CERC) (1977) Shore Protection Manual Vol 1, 3rd ed, US Government Printing Office, Washington DC 514pp.
 23. Keddy PA (1982) Quantifying within-lake gradients of wave energy: interrelationships of wave energy, substrate particle size and shoreline plants in Axe Lake, Ontario. *Aqua Bot* **14**: 41-58.
 24. Fonseca MS and Bell SS (1998) Influence of physical setting on seagrass landscapes near Beaufort, North Carolina, USA. *Mar Eco Progr Ser* **171**: 109-21.
 25. Ballantine WJ (1961) A biologically defined exposure scale for comparative description of rocky shores. *Field Studies* **1**: 1-19.
 26. Lewis JR (1964) The Ecology of Rocky Shores. The English Universities Press Ltd, London, UK. 323 pp.
 27. Bell EC and Denny MW (1994) Quantifying "wave exposure": a simple device for recording maximum velocity and results of its use at several field sites. *J Exp Mar Biol Ecol* **181**: 9-29.
 28. Gerard VA (1982) In situ water motion and nutrient uptake by the giant kelp *Macrocystis pyrifera*. *Mar Biol* **69**: 52-4.
 29. Koehl MAR and Alberte RS (1988) Flow, flapping, and photosynthesis of *Nereocystis luetkeana*: a functional comparison of undulate and flat blade morphologies. *Mar Biol* **99**: 435-44.
 30. Larned ST and Atkinson MJ (1997) Effects of water velocity on NH_4 and PO_4 uptake and nutrient-limited growth in the macroalga *Dictyosphaeria cavernosa*. *Mar Ecol Prog Ser* **157**: 295-302.
 31. Shaughnessy FJ (1996) Identification and microgeographic distribution of *Mazzaella splendens* and *Mazzaella linearis* (Gigartinales, Rhodophyta). *Can J Bot* **74**: 999-1008.
 32. Martel, A (1990) Recruitment, post-metamorphic drifting and reproductive output in the herbivorous gastropod *Lacuna* spp. within Kelp canopies and intertidal seaweed communities. PhD Thesis, University of Alberta.
 33. Jokiel PL and Morrissey JL (1993) Water motion on coral reefs: Evaluation of the 'clod-card' technique. *Mar Ecol Prog Ser* **93**: 175-81.
 34. Denny MW (1985) Water motion. In: Handbook of Phycological Methods, Vol IV Ecology, (Edited by Littler MM and Littler DS pp. 7-29, Cambridge University Press, Cambridge, UK.
 35. Denny MW (1988) Biology and the Mechanics of the Wave-Swept Environments. Princeton University Press, Princeton. 329 pp.
 36. Porter ET, Sanford LP and Suttle SE (2000) Gypsum dissolution is not a universal integrator of 'water motion'. *Limnol Oceanogr* **45**(1): 145-58.
 37. McGehee M A (1998) Comparisons of water motion in coral reefs by measuring corrosion rates of dissimilar metals. *Carrib J Sci* **34**(3-4): 286-97.
 38. Jones WE and Demotroploulos A (1968) Exposure to wave action: measurements of an important ecological parameter on rocky shores of Anglesey. *J Exp Mar Biol Ecol* **2**: 46-53.
 39. Gaylord B (1999) Detailing agents of physical disturbance: wave-induced velocities and accelerations on a rocky shore. *J Exp Mar Biol Ecol* **239**: 85-124.
 40. Eckman EJ, Duggins DO and Siddon CE (2003) Current and wave dynamics in the shallow subtidal: implications to the ecology of understory and surface canopy kelps. *Mar Ecol Prog Ser* **265**: 45-56.